

Installing TrafficDirector Software

Introduction

This chapter describes the installation procedure for the TrafficDirector software.

If you have obtained the TrafficDirector software as a component of CiscoWorks for Switched Internetworks (CWSI) please follow the installation instructions for that bundle.

Installation Prerequisites

Before you begin the installation procedure, check to make sure that your system meets the following minimum system requirements:

- IBM PC or compatible
- Windows 3.1, Windows for Workgroups 3.11, Windows 95, or Windows NT
- Winsock-compliant TCP/IP stack (version 1.1 or higher)
- 4 MB RAM minimum
- 15 MB free disk space minimum

Note This installation procedure assumes you have already installed Windows and a TCP/IP Winsock compliant stack on your PC.

The TrafficDirector software is supplied on CD-ROM or on multiple 3.5" diskettes.

Performing the Installation

This section describes the steps needed to install TrafficDirector.

Installation Procedure

The steps below describe the installation procedure. You can install from a CD or from diskettes.

Step 1 Insert the CD into your CD-ROM drive (for example, drive D:) or insert diskette #1 into your disk drive (drive A or B).

Step 2 Select the **Run...** option from the **File** menu of the Windows Program Manager or the Windows 95 Start Menu.

Step 3 If you are installing from CD, type **D:\disk1\setup** (assuming your CD-ROM drive is drive D:) and click on **OK**.

If you are installing from diskettes, type **A:\setup** or **B:\setup**, depending on which drive you are using, and click on **OK**.

You can also use the **Browse...** button to find the **setup.exe** executable file. Click on **OK** when you locate the file, and click on **OK** again to execute the setup program.

The software is installed in the install directory and its sub-directories, as specified by the user at the time of installation. If you are installing from diskettes, mount additional diskettes as prompted by the software.

Step 4 When prompted, specify a destination path where you want the TrafficDirector software to be installed. The default destination path is **C:\TRAFFDIR**.

The Setup program installs TrafficDirector and creates a TrafficDirector icon.

Step 5 Insert the following line in your **AUTOEXEC.BAT** file (and to the **AUTOEXEC.DOS** file for Windows 95):

```
set NSHOME=install_directory
```

install_directory is the drive and directory where you have installed TrafficDirector. For example, **set NSHOME=C:\TRAFFDIR**.

Step 6 Reboot your PC. If your PC automatically runs Windows, exit Windows and return to the MSDOS prompt.

Step 7 From the MSDOS prompt, type:

```
install_directory\bin\instlic
```

This invokes the licensing program for your product.

Step 8 The licensing program prompts you to enter the following information:

- Serial Number
- Password
- Expiration Date

Enter the information provided on the pink or yellow password form, or the permanent password that you've been assigned.

Note The licensing program is found in the **TRAFFDIR/BIN** directory. If you're using a temporary or evaluation license, you may need to access it again later.

Step 9 Restart Windows.

Step 10 To invoke TrafficDirector, double-click on the TrafficDirector icon.