

# Directory Structure

---

AtmDirector files are placed in directories and subdirectories created on your hard disk during installation. The following list defines the AtmDirector directories and their contents:

- *app-defaults*—contains the AtmDirector file, which includes the AtmDirector application default settings. Refer to Table C-1.
- *bin*—contains the application executables. Table C-2 lists the names and descriptions of the files in the *bin* directory.
- *bitmaps*—contains pixmap files
- *data*—contains runtime data in the *config* and *log* directories. Table C-3 lists the names and descriptions of the files in the *data/config* directory. Table C-4 lists the names and descriptions of the files in the *data/log* directory.
- *etc*—contains miscellaneous files, the *config* directory, and the *help* directory. Table C-5 lists the names and descriptions of the files in the *etc* directory.
- *hyperhelp*—contains files for the HyperHelp application.
- *install*—contains the installation parameters. Table C-6 lists the names and descriptions of the files in the *install* directory.
- *messages*—contains the *AtmDirector.err* file of AtmDirector error messages.
- *mibs*—contains the MIB database files including the *atmd\_mib.txt* file, the AtmDirector MIB database file.

---

**Table C-1      app-defaults Directory**

| Directory   | Description                   |
|-------------|-------------------------------|
| AtmDirector | AtmDirector app-defaults file |

**Table C-2      bin Directory**

| File                     | Description                           |
|--------------------------|---------------------------------------|
| ad__discovery            | Discovery executable                  |
| ad__topology             | Topology executable                   |
| ad_discovery             | Discovery wrapper script              |
| atmdirector <sup>1</sup> | AtmDirector topology wrapper script   |
| cf__pollsrvr             | Polling server executable             |
| cf__srvbrk               | Service request broker executable     |
| cf_pollsrvr              | Polling server wrapper script         |
| cf_srvbrk                | Service request broker wrapper script |

1. The user can execute this file.

**Table C-3      data/config Directory**

| File             | Description                            |
|------------------|----------------------------------------|
| AdDiscovery.conf | Discovery configuration                |
| AdMisc.conf      | Miscellaneous parameters configuration |
| AdSnmpPoll.conf  | SNMP polling parameters configuration  |

---

**Table C-4**      **data/log Directory**

| <b>File</b>          | <b>Description</b>                       |
|----------------------|------------------------------------------|
| RUN_<BACKUP_SRV>.log | Output from Sybase backup server         |
| RUN_<DATA_SRV>.log   | Output from Sybase data server           |
| atmd_setupdb.log     | Log file from atmd_setupdb               |
| atmd_shutdown.log    | Log file from atmd_shutdown              |
| atmd_startup.log     | Log file from atmd_startup               |
| install.log          | Log file from pkgadd of CSOatmd          |
| logfile              | AtmDirector syslog file                  |
| logfile.0            | First backup of AtmDirector syslog file  |
| logfile.1            | Second backup of AtmDirector syslog file |
| logfile.2            | Third backup of AtmDirector syslog file  |
| logfile.3            | Fourth backup of AtmDirector syslog file |

---

**Table C-5**      **etc Directory**

| File                                  | Description                                     |
|---------------------------------------|-------------------------------------------------|
| atmd_buildserver                      | Script to initialize Sybase servers             |
| atmd_createdb                         | Script to create the AtmDirector database       |
| atmd_backup <sup>1</sup>              | Script to back up the AtmDirector database      |
| atmd_dbincl.sh                        | Shell script include file                       |
| atmd_enlarge <sup>1</sup>             | Script to enlarge the AtmDirector database size |
| atmd_include.sh                       | Shell script include file                       |
| atmd_newlog                           | cron script to move AtmDirector syslog          |
| atmd_recover <sup>1</sup>             | Script to recover the AtmDirector database      |
| atmd_schema                           | Script to initialize the AtmDirector database   |
| atmd_setupdb <sup>1</sup>             | Script to drive AtmDirector database setup      |
| atmd_shutdown <sup>1</sup>            | Script to shut down AtmDirector daemons         |
| atmd_startup <sup>1</sup>             | Script to start AtmDirector daemons             |
| config/AdDiscovery.confg <sup>2</sup> | Discovery default configuration                 |
| help/atmd.hlp <sup>2</sup>            | AtmDirector HyperHelp file                      |

1. The user can execute this file.

2. These files are located in a subdirectory in the *etc* file.

**Table C-6**      **install Directory**

| File        | Description                    |
|-------------|--------------------------------|
| atmd_env.sh | AtmDirector environment script |
| pkg_params  | CSCOatmd package parameters    |